
Standard Operating Procedure

<UsingLibrary>

<LedAnalyserBox>

USB Serial Port COM61	
textactivated;	
textactivate	change serial port name;
57600	▼
nousercont	trol:
	display led analyser' baudrate;
select led analyser range	~
textactivated; select led analyser range, before display value;	
select pwm level	~
textactivated;	
	select pwm level;
select led command ∨	
textactivate	ed;
	select led system command; include help(some model return error),version,hardware,serialnumber;
Get Led Port	
clicked;	
	add system serial port to combobox; operate related widgets;
Connect Led Port	
clicked;	
clicked,	use current setting connect serial port; operate related widgets;
Scan Led Port	
clicked;	
	send getHW,capture5pwm01 to system serial ports; if return model,OK,record and display serial port name on textbrowser and lineedit;
Disconnect Led Port	
clicked;	
	disconnect serial port; operate related widgets;
String: 🗸	
nousercont	trol;
	string command; add /r; add /n;
Option:	
nousercontrol;	
	no function;
Disable Pwm 🔘	
usercontro	! ;

cancel pwm parameter at command last;



Version Logs

<20220405 Version 1.02>

adapted to ubuntu kde x11 platform;

<20220209 Version 1.01>

use supertab, supergroupbox api;

<20211003 Version 1.00>

first release;